



PROFILER
TECH

PROFILER SOFTWARE

What's New





PROFILER TECH

MMS7000 Profiler

&

EVOsoft Analysis Software

Release Notes

Document Version:	19.1.24
Applies To:	
EVOsoft Version:	v18.1.15.1
Profiler7000 Version:	v19.1.24.1

COPYRIGHT 2018 © by Profiler Tech Limited. All rights reserved. No part of this document may be reproduced, stored in a retrieval system, or transmitted, in any form or by any means, electronic, mechanical, photocopying, recording, or otherwise, without the prior written permission of Profiler Tech Limited.

Contents

Introduction	3
How to update EVOsoft Desktop Software.....	3
How to update Profiler7000 Handheld App	4
EVOsoft Changes.....	5
Profiler7000 App Changes	5
User Reference Guide Changes.....	5
Technical Support	5

Introduction

This document describes the changes that have been made to the Profiler7000 handheld app, EVOsoft desktop software and the User Reference Guide since the release of v18.1.15.1 of EVOsoft.

How to update EVOsoft Desktop Software

***NOTE:** While updating EVOsoft should not result in any loss of data, it is strongly recommended that you create a backup of your EVOsoft .sdf database files prior to an update, as described in Section 33 of the MMS7000 Profiler & EVOsoft Analysis Software Instrument and Software User Guide.*

To install the new version of EVOsoft software:


1. Download the installer for the latest version of EVOsoft by visiting <http://www.profilertech.com/software-downloads> and clicking on the relevant “**EVOsoft Installer (x64)**” link
2. Once you have downloaded and saved the .zip file, double-click on it to open it, extract the single Windows Installer .msi installer file it contains and save it somewhere on your PC e.g. on your Desktop.
3. Double-click this .msi file and follow the prompts to install the new version.
***NOTE:** if you already have an older version of EVOsoft installed, there is no need to remove it first as it will be updated automatically as part of the install process.*

How to update Profiler7000 Handheld App

NOTE: While updating the Profiler7000 app should not result in any loss of data, it is strongly recommended that you import all data on the device into EVOsoft prior to an update.

To install the new version of the Profiler7000 App that runs on your MMS7000 handheld:

1. Download the installer for the latest version of EVOsoft by visiting <http://www.profilertech.com/software-downloads> and clicking on the relevant “Profiler7000 App Installer” link
2. Once you have downloaded and saved the .zip file, double-click on it to open it, extract the single **Profilertech.Profiler7000.Setup.cab** device application installer file it contains and save it somewhere on your PC e.g. on your Desktop.
3. Connect your MMS7000 device so that you can browse its contents from your PC.
4. Extract the **Profilertech.Profiler7000.Setup.CAB** file above, and save it to your device in **\Storage Card\Profilertech\Software** e.g.



5. Perform a hard reset of the MMS7000 by pressing and holding both the power button and the corresponding button on the other side of the device for 3 seconds until the display turns completely white. Release the buttons and wait for the re-boot to complete:




The Profiler7000 app has now been upgraded and your MMS7000 is ready for use.

EVOsoft Changes

No changes have been made to the EVOsoft desktop software in this release.

Profiler7000 App Changes

- The  key on the MMS7000 handheld is used to power the device on and off. However, when this key is used to turn it off, the MMS7000 doesn't completely power down but instead goes into a low-power 'Sleep Mode'. While in Sleep Mode the MMS7000 still uses a very small amount of battery power and if left like this the battery will eventually go flat, typically in 5-7 days. To resolve this, a new 'System Menu' has been added to the Home Screen that allows the MMS7000 to be completely powered off so the battery will not discharge over time.

User Reference Guide Changes

The EVOsoft Reference Guide has been updated to include new sections on using the new 'System Menu'.

Technical Support

For technical support please contact

Support@profilertech.com

Or visit us on the web at

www.profilertech.com